## 530/630/730 Pn/PnN GSDML compatibility guide

| Table 1 - GSDML compatibility guide — 530/630/730 Pn/PnN                |                       |  |   |
|---|-----------------------|--|---|
| GSDML file (Found on website)   | GSDML<br>release Date | Compatible with pump software versions | Version comments  |
| GSDML-V2.4-Watson Marlow-530_<br>630_730 Profinet Pump-<br>20211116.xml | February 2022         | 0.41.03<br>0.42.03                     | Initial GSDML release   |
| GSDML-V2.4-Watson Marlow-530_<br>630_730 Profinet Pump-<br>20230316.xml | May 2023              | 0.43                                   | Updated Units for<br>Revolution Count and<br>Total Volume<br>Pumped |

## Link to GSDML file location:

1. Navigate to: https://www.wmfts.com/softwareanddevices/

## Notes:

- 1. If your pump software is compatible with multiple GSDML files versions it is recommended to use the latest version available.
- 2. In order to find your pump software version, select **Help**, then **Software** on your pump
- 3. The correct GSDML file version must be used in combination with the pump software versions listed for good communication between the pump and control system.
- 4. Networks using pumps with different software and GSDML versions are acceptable as long as each pump is using the correct GSDML version